

Linux Mint 18

sacar a un usuario de la pantalla de logon

1. `sudo vim /usr/share/mdm/defaults.conf`
2. buscar Exclude y cambiar nobody por la lista de usuarios que no se quiere que aparezca

o

1. ajusta el UID del usuario(s) que no queremos que aparezcan por debajo del «habitual» (1000)
2. `sudo vim /usr/share/mdm/defaults.conf`
3. buscar MinimalUID=1000 y cambiar por el UID a nuestra conveniencia

/via: <https://forums.linuxmint.com/viewtopic.php?t=178215>

system policy prevents modification of network settings for all users

un usuario no-admin no puede conectarse a nuevas redes WIFI, pide permisos de admin (sudo) para añadir la nueva red.

<http://askubuntu.com/questions/244567/remove-sudo-password-when-connecting-to-new-wifi-network>

</etc/polkit-1/localauthority/50-local.d/10-network-manager.pkla>

```
[Let user pupil modify system settings for network]
Identity=unix-user:<user>
Action=org.freedesktop.NetworkManager.settings.modify.system
ResultAny=no
ResultInactive=no
ResultActive=yes
```

otra posible solución, que dicen funciona en Ubuntu 14.04 LTS & 16.04 LTS:

1. `su -`
2. `nano /usr/share/polkit-1/actions/org.freedesktop.NetworkManager.policy`
3. Towards the end of the file, find the section labeled:<action id=«org.freedesktop.NetworkManager.settings.modify.system»>
4. At the the bottom of the org.freedesktop.NetworkManager.settings.modify.system Section, locate the following line of code: <allow_active>auth_admin_keep</allow_active>
5. Change this line to read as follows: <allow_active>yes</allow_active>
6. Restart

From:
<https://miguelangel.torresegea.es/wiki/> - miguel angel torres egea

Permanent link:
<https://miguelangel.torresegea.es/wiki/linux:desktop:mint18?rev=1536304559>

Last update: 07/09/2018 00:15



