

# zsh-autoenv

## configuration

- AUTOENV\_FILE\_ENTER: Name of the file to look for when entering directories. Default: .autoenv.zsh
- AUTOENV\_FILE\_LEAVE: Name of the file to look for when leaving directories. Requires AUTOENV\_HANDLE\_LEAVE=1. Default: .autoenv\_leave.zsh
- AUTOENV\_LOOK\_UPWARDS: Look for zsh-autoenv «enter» files in parent dirs?. Default: 1
- AUTOENV\_HANDLE\_LEAVE: Handle leave events when changing away from a subtree, where an «enter» event was handled? Default: 1
- AUTOENV\_DISABLED: (Temporarily) disable zsh-autoenv. This gets looked at in the chpwd handler. Default: 0
- AUTOENV\_DEBUG: Set debug level. If enabled (> 0) it will print information to stderr.
  - 0: no debug messages
  - 1: generic debug logging
  - 2: more verbose messages about adding/removing files on the internal stack
  - 3: everything

sets xtrace option (set -x) while sourcing env files. Default: 0

## help

- **autostash:**
  - sobreescribe una variable de entorno y la vuelve a dejar como estaba al salir
- **autoenv\_source\_parent**
  - ejecuta los ficheros **.autoenv.zsh** de los directorios superiores
  - .../..
- **autoenv\_append\_path:** Appends path(s) to \$path (\$PATH), if they are not in there already.
- **autoenv\_prepend\_path:** Prepends path(s) to \$path (\$PATH), if they are not in there already.
- **autoenv\_remove\_path:** Removes path(s) from \$path (\$PATH). Returns 0 in case \$path has changed, 1 otherwise.

## azure example

/

```
autostash ARM_ACCESS_KEY=<key>
echo "auto environment enabled (infrastructure)"
```

/infrastructure

```
autoenv_source_parent .../..
az account set --subscription "XXX -PRO - Subscription"
echo "auto environment enabled (pro)"
```

/aks

```
autoenv_source_parent .../..
```

```
autostash ENV_SUBS="XXX - AKS - Subscription"
autostash ENV_RG="XXX-RG-AKS"
autostash ENV_AKS="XXX"
az account set --subscription "$ENV_SUBS"
az aks get-credentials --resource-group ${ENV_RG} --name ${ENV_AKS} --admin
echo "auto environment enabled ($ENV_SUBS)"
echo "aks credentials (${ENV_RG} - ${ENV_AKS})"
```

From:

<https://miguelangel.torresegea.es/wiki/> - **miguel angel torres egea**



Permanent link:

<https://miguelangel.torresegea.es/wiki/linux:zsh:oh-my-zsh:autoenv?rev=1614723246>

Last update: **02/03/2021 14:14**