

zsh-autoenv

configuration

- **AUTOENV_FILE_ENTER**: Name of the file to look for when entering directories. Default: `.autoenv.zsh`
- **AUTOENV_FILE_LEAVE**: Name of the file to look for when leaving directories. Requires `AUTOENV_HANDLE_LEAVE=1`. Default: `.autoenv_leave.zsh`
- **AUTOENV_LOOK_UPWARDS**: Look for zsh-autoenv «enter» files in parent dirs?. Default: 1
- **AUTOENV_HANDLE_LEAVE**: Handle leave events when changing away from a subtree, where an «enter» event was handled? Default: 1
- **AUTOENV_DISABLED**: (Temporarily) disable zsh-autoenv. This gets looked at in the `chpwd` handler. Default: 0
- **AUTOENV_DEBUG**: Set debug level. If enabled (`> 0`) it will print information to `stderr`.
 - 0: no debug messages
 - 1: generic debug logging
 - 2: more verbose messages about adding/removing files on the internal stack
 - 3: everything

sets `xtrace` option (set `-x`) while sourcing env files. Default: 0

usage

- `autoenv-edit`
 - `$AUTOENV_EDITOR`, `$EDITOR`, or `vim` for editing

help

- **autostash**:
 - sobrescribe una variable de entorno y la vuelve a dejar como estaba al salir
- **autoenv_source_parent**
 - ejecuta los ficheros **.autoenv.zsh** de los directorios superiores
 - opcionalmente podemos pasarle un parámetro `./.` para que solo ejecute ciertos niveles atrás ¿?
- **autoenv_append_path**: Appends path(s) to `$path` (`$PATH`), if they are not in there already.
- **autoenv_prepend_path**: Prepends path(s) to `$path` (`$PATH`), if they are not in there already.
- **autoenv_remove_path**: Removes path(s) from `$path` (`$PATH`). Returns 0 in case `$path` has changed, 1 otherwise.

azure example

/

```
autostash ARM_ACCESS_KEY=<key>
echo "auto environment enabled (infrastructure)"
```

/infrastructure

```
autoenv_source_parent ../../..
az account set --subscription "XXX -PRO - Subscription"
echo "auto environment enabled (pro)"
```

/aks

```
autoenv_source_parent ../../..
autostash ENV_SUBS="XXX - AKS - Subscription"
autostash ENV_RG="XXX-RG-AKS"
autostash ENV_AKS="XXX"
az account set --subscription "${ENV_SUBS}"
az aks get-credentials --resource-group ${ENV_RG} --name ${ENV_AKS} --admin
echo "auto environment enabled (${ENV_SUBS})"
echo "aks credentials (${ENV_RG} - ${ENV_AKS})"
```

From:

<https://miguelangel.torresegea.es/wiki/> - miguel angel torres egea

Permanent link:

<https://miguelangel.torresegea.es/wiki/linux:zsh:oh-my-zsh:autoenv?rev=1614724086>

Last update: **02/03/2021 14:28**

